


PDF Export Settings for Quark 9


The Output Styles menu is located under the Edit Menu. You will be creating a New preset.

- Click on New and choose PDF




Pages

- Choose a name for the PDF Style
- Check Include Blank Pages
- Verification should be set to None




Meta Data

- You can type a Subject and Author as seen or leave blank



Hyperlinks

- Uncheck the Include Hyperlinks box, everything else in this window should be grayed out




Compression

Color & Grayscale Images have the same settings

- Compression is set to Manual Zip (8bit)
- Resolution is set to Keep Resolution

Monochrome Images



- Compression is set to CCITT Group4
- Resolution is set to Keep Resolution
- Compress Text and Line Art should be Checked



Color


- Mode is set to Composite
- Setup is Composite CMYK

(If your job is printing with a Spot color you will change the Setup to Composite CMYK+Spot)



Fonts


- Download All Fonts should be Checked



Marks

- Turn Mode to Off

Marks are not necessary because the PDF generated from Quark will define a trim box based off the document size.




Bleed

- Set Bleed Type to Symmetric
- Set the Amount to .25"
- Clip at Bleed Edge should be Checked


Please Note:

We need a minimum of .125" bleed but prefer .25"




Transparency

- Select “Export Transparency Natively”
- Vector Images set to 600dpi
- Blends set to 150dpi
- Drop Shadows set to 150dpi
- Upsample Rotations will be grayed out
- Flattening Resolution set to 300dpi



OPI

- OPI should be Unchecked



JDF

- Output JDF should be Unchecked

